

## OmniVista 4.2.1 R01 Upgrade Matrix

From:	TO:	OV 4.2.1 R01-GA (Build 69)	OV 4.2.1 R01-MR1 (Build 85)
OV 3.5.7		<a href="#"><u>Direct upgrade</u></a>	Step 1: <a href="#"><u>Upgrade to OV 4.2.1 R01-GA</u></a> Step 2: <a href="#"><u>Automatic upgrade to MR1 from VA menu</u></a>
OV 4.1.1 R01		Step 1: <a href="#"><u>Upgrade to OV 4.1.2.R02</u></a> Step 2: <a href="#"><u>*Upgrade to OV 4.1.2 R03</u></a> Step 3: <a href="#"><u>*Upgrade to OV 4.2.1 R01-GA</u></a>	Step 1: <a href="#"><u>Upgrade to OV 4.1.2.R02</u></a> Step 2: <a href="#"><u>*Upgrade to OV 4.1.2 R03</u></a> Step 3: <a href="#"><u>*Upgrade to OV 4.2.1 R01 GA</u></a> Step 4: <a href="#"><u>Automatic upgrade to MR1 from VA menu</u></a>
OV 4.1.2 R01		Step 1: <a href="#"><u>*Upgrade to OV 4.1.2 R03</u></a> Step 2: <a href="#"><u>*Upgrade to OV 4.2.1 R01-GA</u></a>	Step 1: <a href="#"><u>*Upgrade to OV 4.1.2 R03</u></a> Step 2: <a href="#"><u>*Upgrade to OV 4.2.1 R01 GA</u></a> Step 3: <a href="#"><u>Automatic upgrade to MR1 from VA menu</u></a>
OV 4.1.2 R02		Step 1: <a href="#"><u>*Upgrade to OV 4.1.2 R03</u></a> Step 2: <a href="#"><u>*Upgrade to OV 4.2.1 R01-GA</u></a>	Step 1: <a href="#"><u>*Upgrade to OV 4.1.2 R03</u></a> Step 2: <a href="#"><u>*Upgrade to OV 4.2.1 R01 GA</u></a> Step 3: <a href="#"><u>Automatic upgrade to MR1 from VA menu</u></a>
OV 4.1.2 R03		<a href="#"><u>* Direct upgrade</u></a>	Step 1: <a href="#"><u>*Upgrade to OV 4.2.1 R01-GA</u></a> Step 2: <a href="#"><u>Automatic upgrade to MR1 from VA menu</u></a>
OV 4.2.1 R01-GA (Build 69)			<a href="#"><u>Automatic upgrade from VA menu</u></a>

Note: Please refer to the corresponding target Installation Guide in each step for the upgrade instruction (follow the hyperlink to download).

\* This step includes MongoDB Database Password change. Make sure all the steps for changing the password are followed according to the Installation Guide.